

How to change your Router WIFI password?

Option 1: Use the manufacturer application to modify the WiFi name and password.

ASUS ASUS Router / ASUS ExpertWiFi App	TP-Link TP-Link Tether App	Huawei ONR AI Life app
Step 1: Connect your phone to your router WIFI network		
Step 2:		
<ul style="list-style-type: none"> Launch ASUS Router app. Go to Settings > look for Wi-Fi > Wireless settings > Network settings or Network > main network profile. Tap on Network name and Password/Wireless security field and enter a new username and password. Click Apply or Save the changes. 	<ul style="list-style-type: none"> Launch TP-Link Tether App Go to Main screen > Tools > Wireless or Advanced > System Tools > Modify Password. Tap on Network name and Password field and enter a new username and password. Click Save. 	<ul style="list-style-type: none"> Launch AI Life app and tap on your router to enter its management screen. Navigate to Show more > Wi-Fi management > Wi-Fi (or Network > Wi-Fi management > Wi-Fi). Enter a new password in the Wi-Fi password field and tap the checkmark (✓) to save.

Option 2: Use the router Web Interface to modify the wireless name and password.

Step 1 - Connect your computer to the router via wired **or** WiFi connection. Launch a web browser and enter your router LAN IP or router URL in the address bar:

- ASUS: <http://www.asusrouter.com>
- TP-Link: <http://tplinkwifi.net>
- Huawei: 192.168.8.1 or 192.168.1.254 (refer to the label at the bottom of the router)

Step 2 - Key in your router's username and password to log in.

- Look for the default password on the label beneath or behind the router.

Step 3 - Modify Wireless (WiFi) Name and Password

ASUS	TP-Link	Huawei ONR
<ul style="list-style-type: none"> Go to 'Network > Main network profile' or 'Wireless > General'. Click on Network Name (SSID) and password to modify and enter your preferred name and password. Click [Apply] to save the settings. 	<ul style="list-style-type: none"> Go to 'Wireless or Wireless setting' Look for 'SSID' or 'Network name' and enter your preferred name. Go to 'Password or Wireless Security' and enter your preferred name and password. Click Apply to save the settings. 	<ul style="list-style-type: none"> Go to the Wi-Fi or Wireless Settings section. Enter your preferred name and password. Click Save or Apply.

You will likely be disconnected, so reconnect to the new network name and password you just created.